Utroff U

Simple script to have an easy access to utroff tools

(Beta version: user interface may change)

U readme .					2	Two clause BSD License	(
U manual .					3	Tables	,
Changes of I	Ţ				5		

U readme

Readme

Since *utroff*, *groff* and *Heirloom Troff* share some of the same utilities, it is wise to install each of them in three different part of the system. And since *groff* is sometimes a system dependency (at least to format manual pages), it is wise to put the directory of *utroff* at the end of your **PATH**.

The U script sets the **PATH** and configure some others environment variables to use easily the *utroff* utilities.

Build and install

To build and install, edit the file config.mk from the root directory, and run:

make install

In some circumstances, you might need utroff tools themselves to build the manual pages. In that case, build and install binaries before manual pages like this:

make installbin make installman

You can uninstall files and clean the working directory:

make uninstall make clean

For a more complete description of the build process, look at the README in the root directory.

License

U and its man page are distributed under a two clause BSD license 1.

Help and bugs

Don't hesitate to ask questions at help at utroff dot org. Please, send bugs and patches at help at utroff dot org.

¹ See p. 6.

U manual

Name

U - Set environment variables to use Utroff

Synopsis

@BINDIR@/U [command]

. @BINDIR@/U

Description

Utroff, Heirloom Troff and Groff share some of the same utilities, even if their source code differ. To avoid conflicts, it is wise to put the *utroff* utilities at the end of your **PATH**, which is not handfull for a daily usage. The **U** script will set your **PATH** and some environment variable to use *utroff* easily.

Followed by a *command*, U will set the environment variables for this onliest *command*. With no argument, it can be sourced to set or reset the *Utroff* environment.

The following environments variable are currently set by U:

PATH To be sure that the *utroff* executables are the first found on the PATH.

MANPATH

To be sure that the *utroff* manual pages are the first found on the MANPATH.

TROFFONTS

To find the Libertine OpenType font.

TROFFMACS

To find the utmac macros files.

PS1 When sourced, **U** lightly modify your prompt.

There is one important environment variable that U does not set:

UTMAC

A user defined macro that utmac macros will load. This macro can be used to source a macro which sets your locale (such as u-en or u-fr), and a macro which sets your preferred font (such as u-libertine and u-apolline).

Example

```
# command
U troff -muh f.tr | U dpost | ps2pf -> file.pdf
U ugrind g.tr | U nroff -mut > g.txt
U man refer
# session
. U
troff -muh f.tr | dpost | ps2pdf - > file.pdf
ugrind g.tr | nroff -mut > g.txt
man refer
. U
```

See also

utroff(7).

License

 $\mathbf U$ and this man page are distributed under a two clause BSD $^{\scriptscriptstyle 1}$ license.

Help and bugs

Don't hesitate to ask questions at help at utroff dot org. Please, send bugs and patches at help at utroff dot org.

Author

Written by Pierre-Jean FICHET.

¹ See p. 6.

Changes of U

2014/03/17 13 :23 :48 VERSION-0.4

- U.sh : Fix Remove bashisms (bug report by fravashyo).
- U.sh: Fix colon separated list of directory.
- U.sh : Fix licence date.

2014/03/13 09 :46 :29 VERSION-0.3

– U.tr : Fix typo, since u has been renamed U.

2014/03/12 13 :59 :49 VERSION-0.2

– all : rename u to U, to avoid conflicts with plan9 u.

2013/11/14 12 :16 :52 VERSION-0.1

- Initial revision.

Two clause BSD License

Copyright (c) 2012-2014

Pierre-Jean Fichet. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met :

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of
 conditions and the following disclaimer in the documentation and/or other materials
 provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE REGENTS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE REGENTS OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Tables

Table of content

Utroff U															1
U readme															2
Readme															2
Build and instal	1.														2
License															2
Help and bugs															2
U manual															3
Name															3
Synopsis															3
Description .															3
Example															3
See also															4
License															4
Help and bugs															4
Author															4
Changes of U .															5
2014/03/17 13	3:23	:48	VE	RS	O	V-0.	.4								5
2014/03/13 0	9 :46	:29	VE	RS	O	V-0.	.3								5
2014/03/12 13	3 :59	:49	VE	RS	O	V-0.	.2								5
2013/11/14 12	2:16	:52	VE	RS	O	V-0.	.1								5
Two clause BSD Li	cense														6
Tables															7
Table of content	t.														7